

1. Installing the SecureW2 Client



Disclaimer

The software described in this document is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Copyright Notice

Copyright © 2009 SecureW2 B.V.

All rights reserved

Released: Juli 2009

This document may not, in whole or in part, be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form without prior consent in writing from SecureW2 B.V.

Every effort has been made to ensure the accuracy of this manual. However, SecureW2 makes no warranties with respect to this documentation and disclaims any implied warranties of merchantability and fitness for a particular purpose. SecureW2 shall not be liable for any errors or for incidental or consequential damages in connection with the furnishing, performance, or use of this manual or the examples herein. The information of this document is subject to change without notice.

Trademarks

SecureW2 is a trademark of SecureW2 B.V.

Other product names mentioned in this manual may be trademarks or registered trademarks of their related companies and are the sole property of their respective manufacturers.

1.Windows XP/2K/Vista

1.1. Prerequisites

Make sure you have the following services running before installing:

- Wireless Zero Configuration;
- Wired Auto Configuration (Vista/XP SP3)
- EapHost service (Vista).

1.1.1 Installation

To install the SecureW2 Client, do the following:

1. Download the latest SecureW2_Client_xxx.zip file from the website <http://www.securew2.com/>
2. Unzip the SecureW2_Client_xxx.zip file to a temporary folder on your computer;
3. Double click on the SecureW2_Client_xxx.exe file and follow the instructions of the installation program;
4. Reboot the computer when prompted.

Once successfully installed, you can configure SecureW2, see for User Guide more information.

1.1.2 Un-installation

To uninstall the SecureW2 Client, simply use the "Remove Programs" application in the "Settings/System" folder or select the "Uninstall" option in the Programs/SecureW2 from your start menu.

2.Windows CE

2.1. Prerequisites

- Microsoft Pocket PC 2003 (Windows Mobile) or later (If your handheld runs an older version, you may be able to upgrade. Contact your vendor for more information);
- A wireless/wired NIC that supports 802.1x;
- ActiveSync installed on your desktop.

1.1.3 Installation

To install the SecureW2 Client, do the following:

1. Make sure your handheld is connected to your computer and that ActiveSync is installed and running;
2. Download the latest SecureW2_Client_xxx_CE.zip file from the website <http://www.securew2.com/>
3. Unzip the SecureW2_Client_xxx_CE.zip file to a temporary folder on your computer;
4. Double click on the SecureW2_Client_xxx_CE.exe file and follow the instructions of the installation program.

Once successfully installed, you can configure SecureW2 on your device, see for User Guide more information.

1.1.4 Un-installation

To uninstall the SecureW2 Client, simply use the “Remove Programs” application in the “Settings/System” folder on your handheld.